

## **Sparta Robotics**

Dynamixel library for NVIDIA Jetson TK1 (Adapted from Savage Electronics  
Dynamixel Library Arduino PDL)

### **begin()**

#### Description

Initialize the serial communication.

#### Syntax

```
begin ( serialPort, baudRate, dataPin );  
begin ( serialPort, baudRate );
```

#### Parameters

serialPort - serial device

baudRate - serial transmission in bps

dataPin - pin for data transmit and receive

#### Example

```
Mx28.begin("/dev/ttyTHS0", B1000000, 166);  
Mx28.begin("/dev/ttyUSB0", B1000000);
```

### **disconnect()**

#### Description

Deinitialize the serial communication.

#### Syntax

```
Disconnect ( );
```

#### Parameters

none

#### Example

```
Mx28.disconnect();
```

## **reset()**

### Description

Return to the factory settings of the servomotor.

### Syntax

```
reset ( ID);
```

### Parameters

ID - identification number of the servomotor

### Example

```
Mx28.reset(1);
```

## **ping()**

### Description

Send a question to the servo motor status.

### Syntax

```
ping ( ID);
```

### Parameters

ID - identification number of the servomotor

### Example

```
Mx28.ping(1);
```

## **setID()**

### Description

Change the ID of the servomotor.

### Syntax

```
setID ( ID, newID);
```

### Parameters

ID - identification number of the servomotor  
newID - new identification number of the servomotor

#### Example

```
Mx28.setID(1, 2);
```

### **setBD()**

#### Description

Change the Baud Rate of the servomotor

#### Syntax

```
setBD ( ID, baudRate);
```

#### Parameters

ID - identification number of the servomotor  
baudRate - serial transmission speed in bps

#### Example

```
Mx28.setBD(1, 115200);
```

### **move()**

#### Description

Move the actuator to the position indicated.

#### Syntax

```
move ( ID, Position);
```

#### Parameters

ID - identification number of the servomotor  
Position - servo position 0 to 4095 ( 0 to 360 degrees)

#### Example

```
Mx28.move(1, 2048);
```

## **moveSpeed()**

### Description

Move the actuator to the position indicated airtpeed.

### Syntax

```
moveSpeed ( ID, Position, Speed);
```

### Parameters

ID - identification number of the servomotor

Position - servo position 0 to 4095 ( 0 to 360 degrees)

Speed - speed that will move the servo 0 to 1023

### Example

```
Mx28.moveSpeed(1, 2048, 1023);
```

## **moveDeg()**

### Description

Move the actuator to the position indicated (in degrees).

### Syntax

```
move ( ID, Degrees);
```

### Parameters

ID - identification number of the servomotor

Degrees - servo position -180 to 180 in degrees

### Example

```
Mx28.moveDeg(1, -45);
```

## **moveSpeedDeg()**

### Description

Move the actuator to the position (in degrees) indicated airtpeed.

### Syntax

`moveSpeedDeg ( ID, Degrees, Speed);`

#### Parameters

ID - identification number of the servomotor

Degrees - servo position -180 to 180 in degrees

Speed - speed that will move the servo 0 to 1023

#### Example

`Mx28.moveSpeed(1, -45, 1023);`

### **setEndless()**

#### Description

Enables or disables continuous mode servo motor rotation.

#### Syntax

`setEndless ( ID, Status);`

#### Parameters

ID - identification number of the servomotor

Status - on or off the Endless ( ON or OFF) mode

#### Example

`Mx28.setEndless(1, ON);`

### **turn()**

#### Description

Servomotor rotates to the right or left and the speed indicated only if in continuous rotation mode.

#### Syntax

`turn ( ID, Side, Speed);`

#### Parameters

ID - identification number of the servomotor

Side - direction in which to rotate (RIGHT or LEFT)

Speed - speed that will move the servo 0-1020

### Example

```
Mx28.turn(1, LEFT, 1000);
```

## **moveRW()**

### Description

Save the instruction that moves the actuator to the position indicated.

### Syntax

```
moveRW ( ID, Position)
```

### Parameters

ID - identification number of the servomotor

Position - servo position 0 to 4095 ( 0 to 360 degrees)

### Example

```
Mx28.moveRW(1, 2048);
```

## **moveSpeedRW()**

### Description

Save the instruction that moves the actuator to the position indicated airspeed.

### Syntax

```
moveSpeedRW ( ID, Position, Speed)
```

### Parameters

ID - identification number of the servomotor

Position - servo position 0 to 4095 ( 0 to 360 degrees)

Speed - speed that will move the servo 0 to 1023

### Example

```
Mx28.moveSpeedRW(1, 2048, 1023);
```

## **action()**

### Description

Executes the instruction stored in the servomotor.

### Syntax

```
action ( );
```

### Parameters

none

### Example

```
Mx28.action();
```

## **torqueStatus()**

### Description

Enables or disables the torque on the servomotor.

### Syntax

```
torqueStatus (ID, Status);
```

### Parameters

ID - identification number of the servomotor

Status - on or off the touch ( ON or OFF)

### Example

```
Mx28.torqueStatus(1, ON);
```

## **ledStatus()**

### Description

Turns the LED on the back of the servomotor.

### Syntax

```
LEDStatus ( ID, Status);
```

### Parameters

ID - identification number of the servomotor  
Status - on or off ( ON or OFF) LED

#### Example

```
Mx28.ledStatus(1, ON);
```

### **readTemperature()**

#### Description

Reads the internal temperature of the servomotor.

#### Syntax

```
readTemperature (ID);
```

#### Parameters

ID - identification number of the servomotor

#### Example

```
var = Mx28.readTemperature(1);
```

### **readVoltage()**

#### Description

Reads the supply voltage of the servomotor.

#### Syntax

```
readVoltage (ID);
```

#### Parameters

ID - identification number of the servomotor

#### Example

```
var = Mx28.readVoltage(1);
```

### **readPosition()**

#### Description

Reads the position in which the actuator is located.



### Syntax

readPosition (ID);

### Parameters

ID - identification number of the servomotor

### Example

```
var = Mx28.readPosition(1);
```

## **readSpeed()**

### Description

Read the rpm of the servomotor.

### Syntax

readSpeed (ID);

### Parameters

ID - identification number of the servomotor

### Example

```
var = Mx28.readSpeed(1);
```

## **readLoad()**

### Description

Read the current used by the servomotor.

### Syntax

readLoad (ID);

### Parameters

ID - identification number of the servomotor

### Example

```
var = Mx28.readLoad(1);
```

## **setTempLimit()**

### Description

Configures a maximum operating temperature of the servomotor.

### Syntax

```
setTempLimit ( ID, Temperature);
```

### Parameters

ID - identification number of the servomotor

Temperature - the maximum temperature to which the servo motor will work

### Example

```
Mx28.setTempLimit(1, 80);
```

## **setAngleLimit()**

### Description

Sets a maximum angle CW and CCW operating servomotor.

### Syntax

```
setTempLimit ( ID, CW, CCW);
```

### Parameters

ID - identification number of the servomotor

CW - maximum angle to clockwise

CCW - maximum angle against clockwise

### Example

```
Mx28.setAngleLimit(1, 45, 45);
```

## **setVoltageLimit()**

### Description

Set a minimum and maximum operating voltage on the actuator.

### Syntax

```
setVoltageLimit ( ID, minVoltage, maxVoltage);
```

### Parameters

ID - identification number of the servomotor

minVoltage - minimum operating voltage of the servomotor

maxVoltage - maximum operating voltage of the servomotor

### Example

```
Mx28.setVoltageLimit(1, 70, 160);
```

## **setMaxTorque()**

### Description

Sets a maximum torque on the actuator.

### Syntax

```
setMaxTorque ( ID, Maxtorque);
```

### Parameters

ID - identification number of the servomotor

Maxtorque - servomotor maximum torque ( 0-1023)

### Example

```
Mx28.setMaxTorque(1, 1023);
```

## **setSRL()**

### Description

Sets the Status Return Level of servomotor.

### Syntax

```
setSRL ( ID, SRL);
```

### Parameters

ID - identification number of the servomotor

SRL - ( 0 Return none), ( read Return 1), ( 2 Return all)

### Example

```
Mx28.setSRL(1, 2);
```

## **setRDT()**

### Description

Return Delay Time Sets the servomotor.

### Syntax

```
setRDT ( ID, RDT);
```

### Parameters

ID - identification number of the servomotor

RDT - time information return ( 0-255) \* 2us

### Example

```
Mx28.setRDT(1, 255);
```

## **setLEDAAlarm()**

### Description

Set the alarm LED servomotor.

### Syntax

```
setLEDAAlarm ( ID, LEDAlarm);
```

### Parameters

ID - identification number of the servomotor

LEDAlarm - alarm LED ( 0-255)

### Example

```
Mx28.setLEDAAlarm(1, 255);
```

## **setShutdownAlarm()**

### Description

Set the alarm off the booster.

### Syntax

```
setShutdownAlarm ( ID, shutdownAlarm);
```

### Parameters

ID - identification number of the servomotor  
shutdownAlarm - alarm LED ( 0-255)

### Example

```
Mx28.setShutdownAlarm(1, 255);
```

## **setCMargin()**

### Description

Compliance Margin Sets the servomotor.

### Syntax

```
setCMargin ( ID, CWCM, CCWCM);
```

### Parameters

ID - identification number of the servomotor  
CWCM - CW Compliance Margin ( 0-255)  
CCWCM - CCW Compliance Margin ( 0-255)

### Example

```
Mx28.setCMargin(1, 1, 1);
```

## **setCSlope()**

### Description

Set the servomotor Compliance Slop.

### Syntax

```
setCSlope ( ID, CWCS, CCWCS);
```

### Parameters

ID - identification number of the servomotor  
CWCS - CW Complaine Slope ( 0-255)  
CCWCS - CCW Compliance Slope ( 0-255)

### Example

```
Mx28.setCSlope(1, 64, 64);
```

## **setPunch()**

### Description

Punch Sets the maximum current of servomotor.

### Syntax

```
setPunch ( ID, Punch);
```

### Parameters

ID - identification number of the servomotor

Punch - current in the servomotor ( 0-1023)

### Example

```
Mx28.setPunch(1, 1023);
```

## **moving()**

### Description

Check or read if the servomotor is moving.

### Syntax

```
moving ( ID);
```

### Parameters

ID - identification number of the servomotor

### Example

```
Var = Mx28.moving(1);
```

## **lockRegister()**

### Description

Blocks 24 to 35 records of the servomotor

### Syntax

```
lockRegister ( ID);
```

### Parameters

ID - identification number of the servomotor

### Example

```
Var = Mx28.lockRegister(1);
```

## **RWStatus()**

### Description

Determines REG\_RITE state servomotor.

### Syntax

```
RWStatus ( ID);
```

### Parameters

ID - identification number of the servomotor

### Example

```
Var = Mx28.RWStatus(1);
```